



Aras Innovator 33

Upgrading to Release 33 from Release 14+

Document #: D-008132

Last Modified: 9/26/2024

Copyright Information

Copyright © 2024 Aras Corporation. All Rights Reserved.

Aras Corporation
100 Brickstone Square
Suite 100
Andover, MA 01810
Phone: 978-691-8900

E-mail: support@aras.com

Website: <https://www.aras.com/>

Notice of Rights

Copyright © 2024 by Aras Corporation and/or its affiliates. All rights reserved.

This document is protected by U.S. and international copyright laws and conventions. No copyright may be obscured or removed from this document. This document may not be modified or altered, or reproduced or transmitted in any form, without the explicit permission of the copyright holder.

Aras Innovator, Aras, and the Aras Corp "A" logo are registered trademarks of Aras Corporation in the United States and other countries.

All other trademarks referenced herein are the property of their respective owners.

Notice of Liability

THIS DOCUMENT IS PROVIDED FOR INFORMATIONAL PURPOSES ONLY, AND THE CONTENTS HEREOF ARE SUBJECT TO CHANGE WITHOUT NOTICE. THE INFORMATION CONTAINED IN THIS DOCUMENT IS DISTRIBUTED ON AN "AS IS" BASIS, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE OR A WARRANTY OF NON-INFRINGEMENT. ARAS SHALL HAVE NO LIABILITY TO ANY PERSON OR ENTITY WITH RESPECT TO ANY LOSS OR DAMAGE CAUSED OR ALLEGED TO BE CAUSED DIRECTLY OR INDIRECTLY BY THE INFORMATION CONTAINED IN THIS DOCUMENT OR BY THE SOFTWARE OR HARDWARE PRODUCTS DESCRIBED HEREIN.

Table of Contents

Send Us Your Comments	4
1 Overview.....	5
2 Prerequisites	6
2.1 Checking for Eligibility	6
2.2 Required Tools and Materials	8
2.2.1 Aras Update Tool.....	8
2.2.2 Aras Innovator 33 Patch.....	8
2.2.3 Checking for Additional Features	8
2.3 Feature License Key	9
2.3.1 Requesting a Feature License	9
2.3.2 Installing the License	9
3 Upgrade Process	11
3.1 Upgrading Innovator Server	11
3.1.1 Notification and Backup.....	11
3.1.2 Upgrade Process.....	12
3.2 Upgrading Aras Visual Collaboration	18
3.3 Upgrading HTML to PDF Converter.....	19
3.4 Confirming the Patch.....	20
3.4.1 Testing Your Upgrade	21

Send Us Your Comments

Aras Corporation welcomes your comments and suggestions on the quality and usefulness of this document. Your input is an important part of the information used for future revisions.

- Did you find any errors?
- Is the information clearly presented?
- Do you need more information? If so, where and what level of detail?
- Are the examples correct? Do you need more examples?
- What features did you like most?

If you find any errors or have any other suggestions for improvement, indicate the document title, and the chapter, section, and page number (if available).

You can send comments to us in the following ways:

Email:

TechDocs@aras.com

Subject: Aras Product Documentation

Or,

Postal service:

Aras Corporation
100 Brickstone Square
Suite 100
Andover, MA 01810
Attention: Aras Technical Documentation

If you would like a reply, provide your name, email address, address, and telephone number.

If you have usage issues with the software, visit <https://www.aras.com/support/>

1 Overview

The process of updating Aras Innovator is constantly evolving to make upgrades faster and easier.

The information in this document outlines the steps required for upgrading Aras Innovator Release 14 or newer to 33. The changes outlined in this release are seen as 'core' changes from the Aras Innovator 14 or newer platforms. These changes affect both the database and the code tree. Subscribers are encouraged to contact Aras Support if assistance is needed to execute the steps outlined in this document.

Note: If the current implementation of Aras Innovator includes add-on applications or critical customizations that need to be preserved during the upgrade process, please contact Aras Support (support@aras.com) for assistance.

2 Prerequisites

To upgrade Aras Innovator from release 14 or newer to release 33, you need to first check that your software is currently eligible for upgrade. Then, you need to download the necessary materials for upgrade.

2.1 Checking for Eligibility

Use the following steps to check if your code tree and database are eligible for upgrade to Aras Innovator 33.

To check eligibility for upgrade

1. The minimum supported version of SQL Server is 2016. Make sure that the SQL Server where the database of the Aras Innovator instance is installed is SQL 2016 or higher; otherwise, the upgrade process will fail with an error.
2. Log in to Aras Innovator as an administrator.



3. Click the User Menu icon and select **About** from the dropdown menu.
4. Confirm that the dialog shows the following:
 - Aras Innovator Release 14 Build 14.0.0.33343
 - Aras Innovator Release 15 Build 14.0.1.33397
 - Aras Innovator Release 16 Build 14.0.2.33605
 - Aras Innovator Release 17 Build 14.0.3.34066
 - Aras Innovator Release 18 Build 14.0.4.34465
 - Aras Innovator Release 19 Build 14.0.5.34717
 - Aras Innovator Release 20 Build 14.0.6.34944
 - Aras Innovator Release 21 Build 14.0.7.35492
 - Aras Innovator Release 22 Build 14.0.8.35675
 - Aras Innovator Release 23 Build 14.0.9.36073
 - Aras Innovator Release 24 Build 14.0.10.36415
 - Aras Innovator Release 25 Build 14.0.11.36751
 - Aras Innovator Release 26 Build 14.0.12.36913
 - Aras Innovator Release 27 Build 14.0.15.38102
 - Aras Innovator Release 28 Build 14.0.18.39055
 - Aras Innovator Release 29 Build 14.0.20.39432
 - Aras Innovator Release 30 Build 14.0.22.40048
 - Aras Innovator Release 31 Build 14.0.25.40942
 - Aras Innovator Release 32 Build 14.0.28.41847

About



Release 32 Build 14.0.28.41847



MS Build Number: 000000.00

© 2000-2024 Aras Corporation. All rights reserved.

PDF technology powered by PDFNet WebViewer copyright © PDFTron™
Systems Inc., 2001-2014, and distributed by ARAS Corporation under license.
All rights reserved.

Figure 1.

- 5. Click **OK**.
- 6. From the TOC, select **Administration --> Variables**.
- 7. Confirm that one of following sets of variables are listed:

	Version Major	Version Minor	Version ServiceUpdate	Version ServicePack
14	14	0	0	None
15	14	0	1	None
16	14	0	2	None
17	14	0	3	None
18	14	0	4	None
19	14	0	5	None
20	14	0	6	None
21	14	0	7	None
22	14	0	8	None
23	14	0	9	None
24	14	0	10	None



25	14	0	11	None
26	14	0	12	None
27	14	0	15	None
28	14	0	18	None
29	14	0	20	None
30	14	0	22	None
31	14	0	25	None
32	14	0	28	None

If you do not meet the release requirements listed in the previous steps, then you should contact Aras to discuss your upgrade options.

2.2 Required Tools and Materials

If you have successfully met the requirements listed in section 2 Prerequisites, then the next step is to obtain the required upgrade files and utilities.

2.2.1 Aras Update Tool

The first thing you need is the Aras Update tool. This tool can be downloaded from <https://www.aras.com/support/downloads>.

Aras Update should be downloaded and installed locally on every node that is running a component of Aras Innovator.

2.2.2 Aras Innovator 33 Patch

The next thing you need is the actual patch that allows you to upgrade your existing Aras Innovator 14 or newer instance to Aras Innovator 33. Subscribers can obtain this patch from the Aras Innovator 33 CD Image on the Aras FTP site. If you need help accessing the FTP site, contact Aras Support at support@aras.com.

Once connected to the Aras FTP site, browse to the `/InnovatorLatestRelease/Release 33/Release 33 CD Image/Utilities/` folder.

Copy the 'Aras Innovator 33 Patch.zip' file to your local machine.

2.2.3 Checking for Additional Features

Aras Innovator allows for the customization of the Aras Innovator code tree and database that could conflict with the patch that is being applied. To help prevent the possible loss of these customizations, please review the following list of features that could be affected by this patch.

2.2.3.1 Language Packs

The code tree update applied as part of this patch updates the \Innovator\Client\xml folder. The update to this folder requires that any language pack be reviewed and updated for Aras Innovator 33.

To determine what Languages are enabled in your Aras Innovator instance, simply log into Aras Innovator as an Administrator and select **Administration --> Localization --> Languages** from the TOC. If languages other than the default, English, are listed, then it is recommended you check for an updated language pack before upgrading.

Note: For more details, refer section 2.4 'Updating the Resource.Config.xml' of the *Aras Innovator 33 - Language Pack Management* document.

2.2.3.2 Aras Applications and Platform Components

If you are using any of the Aras Applications or Platform Components, you must check the supported releases of Aras Innovator before upgrading. You can either check in the Aras Subscriber Portal at <https://www.aras.com/SubscriberPortal/support.aspx> or contact Aras Corporation Support at support@aras.com.

2.3 Feature License Key

The upgrade scripts for Aras Innovator require an *Aras.ApplyUpdate* Feature in order to run. This Feature is available to subscribers as part of the *Aras.EnterpriseSubscription* package. To check whether a valid Feature License exists in the Aras Innovator Database:

1. Log into Aras Innovator as an administrator.
2. Go to **Administration\Feature Licenses**.
3. Check that *Aras.EnterpriseSubscription* Feature License is present. If this Feature License is found, check the expiration date to confirm that the license is still active.

2.3.1 Requesting a Feature License

In order to request a feature license activation key, customers with an active Aras subscription can send an email to licenses@aras.com or to their account representative using the following format:

- Subject – “Aras Enterprise Subscription Key Required”
- Body - Version of Aras Innovator

You will receive a reply containing the Feature License activation key.

2.3.2 Installing the License

Once you have the activation key, install the feature license as follows:

1. Log into Aras Innovator as an administrator.
2. From the main menu toolbar, select **Tools --> Admin --> Licenses --> Activate Feature**.

Activate Feature ×

Activation Key

Activate

Cancel

3. Paste the acquired activation key and click **Activate Feature** button.
A success message similar to the following should appear.

Activation Successful ×

Aras.EnterpriseSubscription

Expiration Date: 12/31/2024

OK

3 Upgrade Process

This section walks you through applying the Aras Innovator 33 Patch to Aras Innovator Releases 14 or newer. Aras recommends you do a test run of this upgrade on a non-production instance, before attempting this upgrade on your production system.

3.1 Upgrading Innovator Server

Upgrading the production instance of Aras Innovator should be done with planning of a short timetable, and an ability to back out the upgrade if something in the process unexpectedly fails.

The following sections are a rough outline of the steps used when upgrading the Aras Innovator production instance.

3.1.1 Notification and Backup

4. Notify users that the system will be down at a scheduled time, and that they should log out of the system prior to the start of the process.

Note: It is best to give at least 24 hours of notice, as well as a reminder 15 minutes prior to the upgrade.

5. Back up the code tree:

The 'Code Tree' refers to files and folders installed to the disk when Aras Innovator was first installed.

The default path for the Code Tree installation would be something similar to:

C:\Program Files (x86)\Aras\Innovator

With the following contents:

Name	Type	Size
AgentService	File folder	
ConversionServer	File folder	
DB	File folder	
Innovator	File folder	
OAuthServer	File folder	
SelfServiceReporting	File folder	
Tools	File folder	
VaultServer	File folder	
ConversionServerConfig	XML File	5 KB
InnovatorServerConfig	XML File	8 KB
SelfServiceReportConfig	XML File	1 KB

Figure 2.

You can confirm the installation folder with the following steps:

- a. From the Start Menu, select **Start --> Control Panel**.
- b. From the **Control Panel**, select **Programs and Features**.
- c. Right-click on the 'Name' column header and select **More...**
 1. Select the Comments header if it is not checked
 2. Click **OK**.

- d. Search for the **Aras Innovator** entry in the **Programs and Features** window.
- e. View the value set in the **Comments** column for the Aras Innovator entry:

Uninstall or change a program

To uninstall a program, select it from the list and then click Uninstall, Change, or Repair.

Organize ▾		Uninstall				
Name	Publisher	Installed On	Size	Version	Location	
 Aras Innovator	Aras Corporation	11/24/2021	0.98 GB	14.0.0	C:\Program Files (x86)\Aras\Innovator\	

Figure 3.

Once you have determined where the code tree is installed, you would want to back up the folder and all of its contents.

- 6. Disconnect all users from the database.

The easiest way to prevent client sessions from committing any further changes to the database is to change the database connection string in the `InnovatorServerConfig.xml` from `<DB-Connection...` to `<xDB-Connection` and restart the `w3svc` service (IIS). This expires all session and prevents all new connections to the Aras Innovator database through the existing instance.

- 7. Backup the database.

Place this file in a safe location, as it is necessary when you restore from it, if the upgrade fails.

- 8. Enable database connections.

After your database backup has completed, you can enable the database connection string in the `InnovatorServerConfig.xml` by simply changing it from `<xDB-Connection...` to `<DB-Connection` and restarting the `w3svc` service (IIS).

3.1.2 Upgrade Process

The Upgrade Process is handled by the Aras Update tool. But it has to be run locally on each server where an Aras Innovator component is installed.

Warning Before starting the upgrade procedure, confirm all code tree and database components are backed up as described in the section above.

- 1. Copy and unzip the `Aras Innovator 33 Patch.zip` file on the server.
- 2. Launch Aras Update tool as administrator.
- 3. Click on the **Local** button.






Figure 4.

4. Add reference to the unzipped Aras Innovator 33 Patch folder.
 - a. Click on **+ Add package reference**.
 - b. Select the top-level folder containing the patch and click **OK**.

Aras Upgrade Package should be added as shown.




Figure 5.

5. Click on the **Install** button.
6. Select appropriate installation components from the listed modules and click the **Next** button.

- ☒ Upgrade Aras Innovator Server
Apply over Innovator Server directory
- ☒ Upgrade Aras Vault Server
Apply over Vault Server directory
- ☒ Upgrade Aras OAuth Server
Apply over OAuth application directory
- ☒ Upgrade Aras Innovator Database
Import in Innovator Database
- ☒ Upgrade Aras Conversion Server
Apply over Aras Conversion Server directory.
- ☒ Upgrade Aras Agent Service
Apply over Aras Agent Service directory.

Back Next Cancel

Figure 6.

Note: The code tree upgrades will only work correctly if the components are installed locally. Database can be upgraded from any machine that can make a successful http connection to Aras Innovator application.

7. Select the **Detailed Logging** option and then click **Next**.

Aras Update - Select Components for Backup

aras / UPDATE

Select if you want to create a log file to record installation transactions.

Log file location: C:\ProgramData\Aras\ArasUpdate\ArasUpgradePackage\14.30.0.42172\Logs

☒ Create log file including:


☐ Simple logging

☒ Detailed logging

Back Next Cancel

Figure 7.

8. If updating a code tree components, specify the path to the top-level Innovator folder as shown in example below and click **Install**.



Aras Update

aras UPDATE

Enter the following parameters for each component you are going to install and then click Install button to continue.

✓ Upgrade Aras Innovator Server

Path to the common directory where Aras Innovator components are installed
 Browse...

✓ Upgrade Aras Vault Server

Path to the installed Vault Server
 Browse...

✓ Upgrade Aras OAuth Server

Path to the installed OAuth Server
 Browse...

Server URL

Upgrade Aras Innovator Database

✓ Upgrade Aras Conversion Server

Path to the installed Conversion Server
 Browse...

✓ Upgrade Aras Agent Service


Path to the installed Agent Service
 Browse...

Back Install Cancel

Figure 8.

The installation process should run and complete successfully.

9. If updating the database, specify the following information:
 - a. **Server URL:** URL address for Aras Innovator.
 - b. **Database:** Name of the database that should be updated.
 - c. **Username:** Must be root.
 - d. **Password:** Password for root user.
 - e. **SQL Instance:** The name of the SQL Server instance where the database of the upgrading Aras Innovator instance is installed.
 - f. **SQL Database Name:** Name of the database that should be updated.
 - g. **DBA Login Name:** DB admin user with ALTER DATABASE permissions. Default is sa.
 - h. **DBA Password:** Password for DB admin user. Default is sa user.



The image shows a software window titled "Aras Update" with a red header bar. The header contains the "aras" logo and the word "UPDATE" in a red box. In the top right corner, there are window control buttons (minimize, maximize, close) and a help icon (question mark). Below the header, a message states: "Enter the following parameters for each component you are going to install and then click Install button to continue." A section titled "✓ Upgrade Aras Innovator Database" is expanded, showing a list of input fields for database configuration. The fields are: "Server URL" (text box with "http://localhost/InnovatorServer"), "Database" (dropdown menu with "InnovatorSolutions" selected), "Username" (text box with "root"), "Password" (password box with dots), "SQL Instance" (text box with "DatabaseName"), "SQL Database Name" (text box with "InnovatorSolutionss"), "DBA Login Name" (text box with "sa"), and "DBA Password" (password box with dots). At the bottom of the form are three buttons: "Back", "Install", and "Cancel".

Aras Update

aras / UPDATE

Enter the following parameters for each component you are going to install and then click Install button to continue.

✓ Upgrade Aras Innovator Database

Server URL
http://localhost/InnovatorServer

Database
InnovatorSolutions

Username
root

Password
.....

SQL Instance
DatabaseName

SQL Database Name
InnovatorSolutionss

DBA Login Name
sa

DBA Password
.....

Back Install Cancel

Figure 9.

The import process should run and complete successfully.

Note: Remember to disable the **root** user after the import is complete.

- Repeat steps above for all modules as needed until all components of Aras Innovator are upgraded successfully.

Note: If any part of the process fails, or if manual upgrade steps are required, contact Aras Support at support@aras.com.

3.2 Upgrading Aras Visual Collaboration

If your previous version of Aras Innovator had Aras Visual Collaboration enabled, you must update it to include the Aras2DPdfViewer package.

Use the following procedure to upgrade Visual Collaboration:

1. Confirm that a current version of the `Aras.PDFViewer` Feature license is activated in the database:
 - a. Log into Aras Innovator as an administrator.
 - b. Go to **Administration\Feature Licenses** in the TOC and do a search for “`Aras.PDFViewer`” license.
 - c. If the license is not found, subscribers can request a license from licenses@aras.com.
2. Unzip the **ArasPDFViewer.zip** file found in `CD Image\Utilities\` folder.
3. Import the database package with the Package Import Export Utilities. For more information on using this tool, refer to the *Aras Innovator 33 - Package Import Export Utilities* documentation.
 - a. You need to enable the “Super User” login to perform this step.
 - b. Browse to the `\PackageImportExportUtilities\Import\` folder and run the `Import.exe` file




Figure 10.

4. Enter a connection URL for a given Aras Innovator instance in the Server field. By default, it is `http://localhost/InnovatorServer/`.
5. Click the Login button. The Login to Aras Innovator dialog box appears.




Figure 11.

6. Specify the connection information for the given Aras Innovator instance:
 - a. **Database:** a name of a target Aras Innovator database. By default, it is **InnovatorSolutions**.
 - b. **Username:** **root**.
 - c. **Password:** a password for the **root** User. By default, it is **innovator**.
7. Click the **Login** button. Aras Package Import should have successfully connected to the given Aras Innovator instance.
8. Specify the connection information for the PDF Viewer installation modules:
 - a. **Target Release** = 33
 - b. **Description** = PDF Viewer
 - c. **Manifest File Path** = The manifest is found in the folder CD Image\Utilities\ArasPDFViewer\Imports
 - d. **Available for Import** = Check PDFViewer
 - e. **Type** = Merge
 - f. **Mode** = Thorough Mode
9. Click Import to start the utility.
10. After the import has been completed, disable the **Super User** user.

3.3 Upgrading HTML to PDF Converter

If your previous version of Aras Innovator had HTML to PDF Converter enabled, you must upgrade it as well.

1. Copy the Aras HTML to PDF Converter package to a local drive on the Conversion Server.
This Aras HTML to PDF Converter folder is in the Utilities directory of the Aras Innovator CD Image on the Aras FTP website (<ftp://ftp.aras.com/InnovatorLatestRelease/>)
2. Copy the 'ConversionServer' folder to the root directory where the Conversion Server was installed, overwriting the existing 'ConversionServer' folder and its contents.




Figure 10.

3. Restart IIS.

3.4 Confirming the Patch

Use the following steps to check if your code tree and database have applied the upgrade to Aras Innovator 33.

1. Log in to Aras Innovator as an administrator.
2. From the Main Menu select **Help --> About**.
3. Confirm that the dialog shows the following:
 - o Aras Innovator Release 33 Build 14.30.0.42172



Figure 13.

4. Click **OK**.
5. From the TOC, select **Administration --> Variables**.
6. Confirm that following variables are listed:

Name	Value
VersionMajor	14
VersionMinor	30
VersionServicePack	None
VersionServiceUpdate	0

If any part of this test fails, revert to your backups and contact Aras Support at Support@aras.com.

3.4.1 Testing Your Upgrade

Aras recommends you test any critical functionality before going live with any upgrade

- Test critical functionality
- Test the vault
 - Add a new file, view that file, and finally delete that file.
 - View existing file from prior to the upgrade.

If all tests are satisfactory, notify users the system is running again.